

## NAME

AtomTypesFingerprints.pl - Generate atom types fingerprints for SD files

## SYNOPSIS

AtomTypesFingerprints.pl SDFfile(s)...

```
AtomTypesFingerprints.pl [--AromaticityModel AromaticityModelType] [-a, --AtomIdentifierType AtomicInvariantsAtomTypes |
DREIDINGAtomTypes | EStateAtomTypes | MMFF94AtomTypes | SLogPAtomTypes | SYBYLAtomTypes | TPSAAtomTypes | UFFAtomTypes] [
--AtomicInvariantsToUse "AtomicInvariant, AtomicInvariant..."] [--FunctionalClassesToUse "FunctionalClass1, FunctionalClass2..."] [
--AtomTypesSetToUse ArbitrarySize | FixedSize] [--BitsOrder Ascending | Descending] [-b, --BitStringFormat BinaryString |
HexadecimalString] [--CompoundID DataFieldName or LabelPrefixString] [--CompoundIDLabel text] [--CompoundIDMode DataField |
MolName | LabelPrefix | MolNameOrLabelPrefix] [--DataFields "FieldLabel1, FieldLabel2,..."] [-d, --DataFieldsMode All | Common | Specify |
CompoundID] [-f, --Filter Yes | No] [--FingerprintsLabelMode FingerprintsLabelOnly | FingerprintsLabelWithIDs] [--FingerprintsLabel
text] [-h, --help] [-k, --KeepLargestComponent Yes | No] [-m, --mode AtomTypesCount | AtomTypesBits] [-i, --IgnoreHydrogens
Yes | No] [--OutDelim comma | tab | semicolon] [--output SD | FP | text | all] [-o, --overwrite] [-q, --quote Yes | No] [-r, --root
RootName] [-s, --size number] [--ValuesPrecision number] [-v, --VectorStringFormat IDsAndValuesString | IDsAndValuesPairsString |
ValuesAndIDsString | ValuesAndIDsPairsString] [-w, --WorkingDir DirName]
```

## DESCRIPTION

Generate atom types fingerprints for *SDFfile(s)* and create appropriate SD, FP or CSV/TSV text file(s) containing fingerprints bit-vector or vector strings corresponding to molecular fingerprints.

Multiple SDFfile names are separated by spaces. The valid file extensions are *.sdf* and *.sd*. All other file names are ignored. All the SD files in a current directory can be specified either by *\*.sdf* or the current directory name.

The current release of MayaChemTools supports generation of atom types fingerprints corresponding to following -a, --AtomIdentifierTypes:

```
AtomicInvariantsAtomTypes, DREIDINGAtomTypes, EStateAtomTypes,
FunctionalClassAtomTypes, MMFF94AtomTypes, SLogPAtomTypes,
SYBYLAtomTypes, TPSAAtomTypes, UFFAtomTypes
```

Based on the values specified for -a, --AtomIdentifierType along with other specified parameters such as --AtomicInvariantsToUse and --FunctionalClassesToUse, initial atom types are assigned to all non-hydrogen atoms or all atoms in a molecule

Using the assigned atom types and specified -m, --Mode, one of the following types of fingerprints are generated:

```
AtomTypesCount - A vector containing count of atom types
AtomTypesBits - A bit vector indicating presence/absence of atom types
```

For *AtomTypesCount* fingerprints, two types of atom types set size are allowed as value of --AtomTypesSetToUse option:

```
ArbitrarySize - Corresponds to only atom types detected in molecule
FixedSize - Corresponds to fixed number of atom types previously defined
```

For *AtomTypesBits* fingerprints, only *FixedSize* atom type set is allowed.

*ArbitrarySize* corresponds to atom types detected in a molecule where as *FixedSize* implies a fix number of all possible atom types previously defined for a specific -a, --AtomIdentifierType.

Fix number of all possible atom types for supported *AtomIdentifierTypes* in current release of MayaChemTools are:

AtomIdentifier	Total	TotalWithoutHydrogens
DREIDINGAtomTypes	37	34
EStateAtomTypes	109	87
MMFF94AtomTypes	212	171
SLogPAtomTypes	72	67
SYBYLAtomTypes	45	44
TPSAAtomTypes	47	47
UFFAtomTypes	126	124

The current release of MayaChemTools generates the following atom types fingerprints bit-vector and vector strings:

```
FingerprintsVector;AtomTypesCount:AtomicInvariantsAtomTypes:ArbitraryS
ize;10;NumericalValues;IDsAndValuesString;C.X1.B01.H3 C.X2.B02.H2 C.X2
.B03.H1 C.X3.B03.H1 C.X3.B04 F.X1.B01 N.X2.B02.H1 N.X3.B03 O.X1.B01.H1
O.X1.B02;2 4 14 3 10 1 1 1 3 2
```

```
FingerprintsVector;AtomTypesCount:DREIDINGAtomTypes:ArbitrarySize;8;Nu
```

```
mericalValues;IDsAndValuesString;C_2 C_3 C_R F_ N_3 N_R O_2 O_3;2 9 22
1 1 1 2 3
```

```
FingerprintsVector;AtomTypesCount:DREIDINGAtomTypes:FixedSize;34;Order
edNumericalValues;IDsAndValuesString;B_3 B_2 C_3 C_R C_2 C_1 N_3 N_R N
_2 N_1 O_3 O_R O_2 O_1 F_ Al3 Si3 P_3 S_3 Cl Ga3 Ge3 As3 Se3 Br In3 Sn
3 Sb3 Te3 I_ Na Ca Fe Zn;0 0 9 22 2 0 1 1 0 0 3 0 2 0 1 0 0 0 0 0 0 0
0 0 0 0 0 0 0 0 0 0 0
```

```
FingerprintsBitVector;AtomTypesBits:DREIDINGAtomTypes:FixedSize;34;Bin
aryString;Ascending;0011101100101010000000000000000000000000
```

```
FingerprintsVector;AtomTypesCount:EStateAtomTypes:ArbitrarySize;11;Num
ericalValues;IDsAndValuesString;aaCH aasC aasN dO dssC sCH3 sF sOH ssC
H2 ssNH sssCH;14 8 1 2 2 2 1 3 4 1 3
```

```
FingerprintsVector;AtomTypesCount:EStateAtomTypes:FixedSize;87;Ordered
NumericalValues;IDsAndValuesString;sLi ssBe ssssBem sBH2 ssBH sssB sss
sBm sCH3 dCH2 ssCH2 tCH dsCH aaCH sssCH ddC tsC dssC aasC aaaC sssC s
NH3p sNH2 ssNH2p dNH ssNH aaNH tN sssNHp dsN aaN sssN ddsN aasN ss...;
0 0 0 0 0 0 2 0 4 0 0 14 3 0 0 2 8 0 0 0 0 0 0 1 0 0 0 0 0 0 1 0 3 2 0 0
0 0 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0...
```

```
FingerprintsBitVector;AtomTypesBits:EStateAtomTypes:FixedSize;87;Binar
yString;Ascending;000000010100110011000000100000001011000010000000000
0000000000000000000000000000000000000000000000000000000000000000
```

```
FingerprintsVector;AtomTypesCount:FunctionalClassAtomTypes:ArbitrarySi
ze;8;NumericalValues;IDsAndValuesString;Ar Ar.HBA HBA HBA.HBD HBD Hal
NI None;22 1 2 3 1 1 1 10
```

```
FingerprintsVector;AtomTypesCount:MMFF94AtomTypes:ArbitrarySize;13;Num
ericalValues;IDsAndValuesString;C5A C5B C=ON CB COO CR F N5 NC=O O=CN
O=CO OC=O OR;2 2 1 18 1 9 1 1 1 1 1 1 2
```

```
FingerprintsVector;AtomTypesCount:MMFF94AtomTypes:FixedSize;171;Ordere
dNumericalValues;IDsAndValuesString;CR C=C CSP2 C=O C=N CGD C=OR C=ON
CONN COO COON COOO C=OS C=S C=SN CSO2 CS=O CSS C=P CSP =C= OR OC=O OC=
C OC=N OC=S ONO2 ON=O OSO3 OSO2 OSO OS=O -OS OPO3 OPO2 OPO -OP -O-...;
9 0 0 0 0 0 0 1 0 1 0 0 0 0 0 0 0 0 0 0 0 0 2 1 0 0 0 0 0 0 0 0 0 0
0 0 0 0 1 0 1 0 0 0 0 0 0 1 0 0 0 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0
0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 ...
```

```
FingerprintsBitVector;AtomTypesBits:MMFF94AtomTypes:FixedSize;171;Bina
ryString;Ascending;1000000101000000000000110000000000000000101000000100
0100000000000000000000000000000000000000000000000000000000000000
00000000110000000000000000001000000000000000000000000000000000
```

```
FingerprintsVector;AtomTypesCount:SLogPAtomTypes:ArbitrarySize;16;Nume
ricalValues;IDsAndValuesString;C1 C10 C11 C14 C18 C20 C21 C22 C5 CS F
N11 N4 O10 O2 O9;5 1 1 1 14 4 2 1 2 2 1 1 1 1 3 1
```

```
FingerprintsVector;AtomTypesCount:SLogPAtomTypes:FixedSize;67;OrderedN
umericalValues;IDsAndValuesString;C1 C2 C3 C4 C5 C6 C7 C8 C9 C10 C11 C
12 C13 C14 C15 C16 C17 C18 C19 C20 C21 C22 C23 C24 C25 C26 C27 CS N1 N
2 N3 N4 N5 N6 N7 N8 N9 N10 N11 N12 N13 N14 NS O1 O2 O3 O4 O5 O6 O7 O8
O9 O10 O11 O12 OS F Cl Br I Hal P Sl S2 S3 Me1 Me2;5 0 0 0 2 0 0 0 0 1
1 0 0 1 0 0 0 14 0 4 2 1 0 0 0 0 2 0 0 0 1 0 0 0 0 0 1 0 0 0 0...
```

```
FingerprintsBitVector;AtomTypesBits:SLogPAtomTypes:FixedSize;67;Binary
String;Ascending;10001000011001000101110000010001000000100000100000011
00010000000000000000
```

```
FingerprintsVector;AtomTypesCount:SYBYLAtomTypes:ArbitrarySize;9;Numer
icalValues;IDsAndValuesString;C.2 C.3 C.ar F N.am N.ar O.2 O.3 O.co2;2
9 22 1 1 1 1 2 2
```

```
FingerprintsVector;AtomTypesCount:SYBYLAtomTypes:FixedSize;44;OrderedNumericalValues;IDsAndValuesString;C.3 C.2 C.1 C.ar C.cat N.3 N.2 N.1 N.ar N.am N.pl3 N.4 O.3 O.2 O.co2 S.3 S.2 S.o S.o2 P.3 F Cl Br I ANY HAL HET Li Na Mg Al Si K Ca Cr.th Cr.oh Mn Fe Co.oh Cu Zn Se Mo Sn;9 2 0 22 0 0 0 0 0 1 1 0 0 2 1 2 0 0 0 0 0 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0
```

```
FingerprintsBitVector;AtomTypesBits:SYBYLAtomTypes:FixedSize;44;BinaryString;Ascending;1101000011001110000001000000000000000000000000
```

[illegible]

```
FingerprintsBitVector;AtomTypesBits:TPSAAAtomTypes:FixedSize;47;BinaryS
tring;Ascending;00000001000000000000000100000000110000000000000000
```

```
FingerprintsVector;AtomTypesCount;UFFAtomTypes;ArbitrarySize;8;Numeric
alValues;IDsAndValuesString;C_2 C_3 C_R F_ N_3 N_R O_2 O_3;2 9 22 1 1
1 2 3
```

```
FingerprintsVector;AtomTypesCount:UFFAtomTypes;124;OrderedNumerical  
Values;IDsAndValuesString;He4+4 Li Be3+2 B_3 B_2 C_3 C_R C_2 C_1 N_3 N_  
R N_2 N_1 O_3 O_3_z O_R O_2 O_1 F_ Ne4+4 Na Mg3+2 Al3 Si3 P_3+3 P_3+5 P_  
_3+q S_3+2 S_3+4 S_3+6 S_R S_2 Cl Ar4+4 K_ Ca6+2 Sc3+3 Ti3+4 Ti6+4 V_3+  
;0 0 0 0 0 12 0 3 0 3 0 1 0 2 0 0 2 0 0 0 0 0 0 0 0 0 0 0 0 0 0  
0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 ...
```

```
FingerprintsVector;AtomTypesCount:UFFAtomTypes:FixedSize;124;OrderedNu
mericalValues;IDsAndValuesString;He4+4 Li Be3+2 B_3 B_2 C_3 C_R C_2 C_
1 N_3 N_R N_2 N_1 O_3 O_3_z O_R O_2 O_1 F_ Ne4+4 Na Mg3+2 Al3 Si3 P_3+
3 P_3+5 P_3+q S_3+2 S_3+4 S_3+6 S_R S_2 Cl Ar4+4 K_ Ca6+2 Sc3+3 Ti...;
0 0 0 0 0 9 22 2 0 1 1 0 0 3 0 0 2 0 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0
0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0
0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0
```

[illegible]

## OPTI ONS

--AromaticityModel MDLAromaticityModel | TriposAromaticityModel | MMFFAromaticityModel | ChemAxonBasicAromaticityModel | ChemAxonGeneralAromaticityModel | DaylightAromaticityModel | MayaChemToolsAromaticityModel

Specify aromaticity model to use during detection of aromaticity. Possible values in the current release are: *MDLAromaticityModel*, *TriposAromaticityModel*, *MMFFAromaticityModel*, *ChemAxonBasicAromaticityModel*, *ChemAxonGeneralAromaticityModel*, *DaylightAromaticityModel* or *MayaChemToolsAromaticityModel*. Default value: *MayaChemToolsAromaticityModel*.

The supported aromaticity model names along with model specific control parameters are defined in AromaticityModelsData.csv, which is distributed with the current release and is available under lib/data directory. Molecule.pm module retrieves data from this file during class instantiation and makes it available to method DetectAromaticity for detecting aromaticity corresponding to a specific model.

-a, --AtomIdentifierType *AtomicInvariantsAtomTypes* | *DREIDINGAtomTypes* | *EStateAtomTypes* | *FunctionalClassAtomTypes* | *MMFF94AtomTypes* | *SLogPAtomTypes* | *SYBYLAtomTypes* | *TPSAAAtomTypes* | *UFFAtomTypes*

Specify atom identifier type to use for assignment of atom types to hydrogen and/or non-hydrogen atoms during calculation of atom types fingerprints. Possible values in the current release are: *AtomicInvariantsAtomTypes*, *DREIDINGAtomTypes*, *EStateAtomTypes*, *FunctionalClassAtomTypes*, *MMFF94AtomTypes*, *SLogPAtomTypes*, *SYBYLAtomTypes*, *TPSAAtomTypes*, *UFFAtomTypes*. Default value: *AtomicInvariantsAtomTypes*.

```
--AtomicInvariantsToUse "AtomicInvariant,AtomicInvariant..."
```

This value is used during *AtomicInvariantsAtomTypes* value of a, --AtomIdentifierType option. It's a list of comma separated valid atomic invariant atom types.

Possible values for atomic invariants are: *AS, X, BO, LBO, SB, DB, TB, H, Ar, RA, FC, MN, SM*. Default value: *AS,X,BO,H,FC*.

The atomic invariants abbreviations correspond to:

AS = Atom symbol corresponding to element symbol

X<n> = Number of non-hydrogen atom neighbors or heavy atoms  
 BO<n> = Sum of bond orders to non-hydrogen atom neighbors or heavy atoms  
 LBO<n> = Largest bond order of non-hydrogen atom neighbors or heavy atoms  
 SB<n> = Number of single bonds to non-hydrogen atom neighbors or heavy atoms  
 DB<n> = Number of double bonds to non-hydrogen atom neighbors or heavy atoms  
 TB<n> = Number of triple bonds to non-hydrogen atom neighbors or heavy atoms  
 H<n> = Number of implicit and explicit hydrogens for atom  
 Ar = Aromatic annotation indicating whether atom is aromatic  
 RA = Ring atom annotation indicating whether atom is a ring  
 FC<+n/-n> = Formal charge assigned to atom  
 MN<n> = Mass number indicating isotope other than most abundant isotope  
 SM<n> = Spin multiplicity of atom. Possible values: 1 (singlet), 2 (doublet) or 3 (triplet)

Atom type generated by AtomTypes::AtomicInvariantsAtomTypes class corresponds to:

AS.X<n>.BO<n>.LBO<n>.<SB><n>.<DB><n>.<TB><n>.H<n>.Ar.RA.FC<+n/-n>.MN<n>.SM<n>

Except for AS which is a required atomic invariant in atom types, all other atomic invariants are optional. Atom type specification doesn't include atomic invariants with zero or undefined values.

In addition to usage of abbreviations for specifying atomic invariants, the following descriptive words are also allowed:

X : NumOfNonHydrogenAtomNeighbors or NumOfHeavyAtomNeighbors  
 BO : SumOfBondOrdersToNonHydrogenAtoms or SumOfBondOrdersToHeavyAtoms  
 LBO : LargestBondOrderToNonHydrogenAtoms or LargestBondOrderToHeavyAtoms  
 SB : NumOfSingleBondsToNonHydrogenAtoms or NumOfSingleBondsToHeavyAtoms  
 DB : NumOfDoubleBondsToNonHydrogenAtoms or NumOfDoubleBondsToHeavyAtoms  
 TB : NumOfTripleBondsToNonHydrogenAtoms or NumOfTripleBondsToHeavyAtoms  
 H : NumOfImplicitAndExplicitHydrogens  
 Ar : Aromatic  
 RA : RingAtom  
 FC : FormalCharge  
 MN : MassNumber  
 SM : SpinMultiplicity

AtomTypes::AtomicInvariantsAtomTypes module is used to assign atomic invariant atom types.

--FunctionalClassesToUse "*FunctionalClass1,FunctionalClass2...*"

This value is used during *FunctionalClassAtomTypes* value of a, --AtomIdentifierType option. It's a list of comma separated valid functional classes.

Possible values for atom functional classes are: *Ar, CA, H, HBA, HBD, Hal, NI, PI, RA*. Default value [ Ref 24 ]: *HBD,HBA,PI,NI,Ar,Hal*.

The functional class abbreviations correspond to:

HBD: HydrogenBondDonor  
 HBA: HydrogenBondAcceptor  
 PI : PositivelyIonizable  
 NI : NegativelyIonizable  
 Ar : Aromatic  
 Hal : Halogen  
 H : Hydrophobic  
 RA : RingAtom  
 CA : ChainAtom

Functional class atom type specification for an atom corresponds to:

Ar.CA.H.HBA.HBD.Hal.NI.PI.RA

AtomTypes::FunctionalClassAtomTypes module is used to assign functional class atom types. It uses following definitions [ Ref 60-61, Ref 65-66 ]:

HydrogenBondDonor: NH, NH2, OH  
 HydrogenBondAcceptor: N[!H], O  
 PositivelyIonizable: +, NH2  
 NegativelyIonizable: -, C(=O)OH, S(=O)OH, P(=O)OH

--AtomTypesSetToUse *ArbitrarySize | FixedSize*

Atom types set size to use during generation of atom types fingerprints.

Possible values for *AtomTypesCount* values of -m, --mode option: *ArbitrarySize | FixedSize*; Default value: *ArbitrarySize*.

Possible values for *AtomTypesBits* value of -m, --mode option: *FixedSize*; Default value: *FixedSize*.

*FixedSize* value is not supported for *AtomicInvariantsAtomTypes* value of -a, --AtomIdentifierType option.

Page 5

```
Extreg
MolID,CompoundName
```

-d, --DataFieldsMode *All | Common | Specify | CompoundID*

Specify how data fields in *SDFFile(s)* are transferred to output CSV/TSV text file(s) along with generated fingerprints for *text* / *all* values of --output option: transfer all SD data field; transfer SD data files common to all compounds; extract specified data fields; generate a compound ID using molname line, a compound prefix, or a combination of both. Possible values: *All | Common | specify | CompoundID*. Default value: *CompoundID*.

-f, --Filter *Yes | No*

Specify whether to check and filter compound data in *SDFFile(s)*. Possible values: *Yes or No*. Default value: *Yes*.

By default, compound data is checked before calculating fingerprints and compounds containing atom data corresponding to non-element symbols or no atom data are ignored.

--FingerprintsLabelMode *FingerprintsLabelOnly | FingerprintsLabelWithIDs*

Specify how fingerprints label is generated in conjunction with --FingerprintsLabel option value: use fingerprints label generated only by --FingerprintsLabel option value or append atom type value IDs to --FingerprintsLabel option value. Possible values: *FingerprintsLabelOnly | FingerprintsLabelWithIDs*. Default value: *FingerprintsLabelOnly*.

This option is only used for *FixedSize* value of -e, --AtomTypesSetToUse option during generation of *AtomTypesCount* fingerprints and ignored for *AtomTypesBits*.

Atom type IDs appended to --FingerprintsLabel value during *FingerprintsLabelWithIDs* values of --FingerprintsLabelMode correspond to fixed number of previously defined atom types.

--FingerprintsLabel *text*

SD data label or text file column label to use for fingerprints string in output SD or CSV/TSV text file(s) specified by --output. Default value: *AtomTypesFingerprints*.

-h, --help

Print this help message.

-i, --IgnoreHydrogens *Yes | No*

Ignore hydrogens during fingerprints generation. Possible values: *Yes or No*. Default value: *Yes*.

For *yes* value of -i, --IgnoreHydrogens, any explicit hydrogens are also used for generation of atom type fingerprints; implicit hydrogens are still ignored.

-k, --KeepLargestComponent *Yes | No*

Generate fingerprints for only the largest component in molecule. Possible values: *Yes or No*. Default value: *Yes*.

For molecules containing multiple connected components, fingerprints can be generated in two different ways: use all connected components or just the largest connected component. By default, all atoms except for the largest connected component are deleted before generation of fingerprints.

-m, --mode *AtomTypesCount | AtomTypesBits*

Specify type of atom types fingerprints to generate for molecules in *SDFFile(s)*. Possible values: *AtomTypesCount or AtomTypesBits*. Default value: *AtomTypesCount*.

For *AtomTypesCount* values of -m, --mode option, a fingerprint vector string is generated. The vector string corresponding to *AtomTypesCount* contains count of atom types.

For *AtomTypesBits* value of -m, --mode option, a fingerprint bit-vector string containing zeros and ones indicating presence or absence of atom types is generated.

For *AtomTypesCount* atom types fingerprints, two types of atom types set size can be specified using -a, --AtomTypesSetToUse option: *ArbitrarySize or FixedSize*. *ArbitrarySize* corresponds to only atom types detected in molecule; *FixedSize* corresponds to fixed number of atom types previously defined.

For *AtomTypesBits* atom types fingerprints, only *FixedSize* is allowed.

Combination of -m, --Mode and --AtomTypesSetToUse along with -a, --AtomIdentifierType allows generation of following different atom types fingerprints:

Mode	AtomIdentifierType	AtomTypesSetToUse
AtomTypesCount	AtomicInvariantsAtomTypes	ArbitrarySize [ Default ]
AtomTypesCount	DREIDINGAtomTypes	ArbitrarySize
AtomTypesCount	DREIDINGAtomTypes	FixedSize
AtomTypesBits	DREIDINGAtomTypes	FixedSize
AtomTypesCount	EStateAtomTypes	ArbitrarySize
AtomTypesCount	EStateAtomTypes	FixedSize
AtomTypesBits	EStateAtomTypes	FixedSize
AtomTypesCount	FunctionalClassAtomTypes	ArbitrarySize
AtomTypesCount	MMFF94AtomTypes	ArbitrarySize

AtomTypesCount	MMFF94AtomTypes	FixedSize
AtomTypesBits	MMFF94AtomTypes	FixedSize
AtomTypesCount	SLogPAtomTypes	ArbitrarySize
AtomTypesCount	SLogPAtomTypes	FixedSize
AtomTypesBits	SLogPAtomTypes	FixedSize
AtomTypesCount	SYBYLAtomTypes	ArbitrarySize
AtomTypesCount	SYBYLAtomTypes	FixedSize
AtomTypesBits	SYBYLAtomTypes	FixedSize
AtomTypesCount	TPSAAtomTypes	FixedSize
AtomTypesBits	TPSAAtomTypes	FixedSize
AtomTypesCount	UFFAtomTypes	ArbitrarySize
AtomTypesCount	UFFAtomTypes	FixedSize
AtomTypesBits	UFFAtomTypes	FixedSize

The default is to generate *AtomicInvariantAtomTypes* fingerprints corresponding to *ArbitrarySize* as value of `--AtomTypesSetToUse` option.

`--OutDelim comma | tab | semicolon`

Delimiter for output CSV/TSV text file(s). Possible values: *comma*, *tab*, or *semicolon* Default value: *comma*.

`--output SD | FP | text | all`

Type of output files to generate. Possible values: *SD*, *FP*, *text*, or *all*. Default value: *text*.

`-o, --overwrite`

Overwrite existing files.

`-q, --quote Yes | No`

Put quote around column values in output CSV/TSV text file(s). Possible values: *Yes* or *No*. Default value: *Yes*.

`-r, --root RootName`

New file name is generated using the root: <Root>.<Ext>. Default for new file names:

<SDFileName><AtomTypesFP>.<Ext>. The file type determines <Ext> value. The sdf, fpf, csv, and tsv <Ext> values are used for SD, FP, comma/semicolon, and tab delimited text files, respectively. This option is ignored for multiple input files.

`-v, --VectorStringFormat ValuesString | IDsAndValuesString | IDsAndValuesPairsString | ValuesAndIDsString | ValuesAndIDsPairsString`

Format of fingerprints vector string data in output SD, FP or CSV/TSV text file(s) specified by `--output` used during <AtomTypesCount> value of `-m, --mode` option. Possible values: *ValuesString*, *IDsAndValuesString* | *IDsAndValuesPairsString* | *ValuesAndIDsString* | *ValuesAndIDsPairsString*.

Default value during *ArbitrarySize* value of `-e, --AtomTypesSetToUse` option: *IDsAndValuesString*. Default value during *FixedSize* value of `-e, --AtomTypesSetToUse` option: *ValuesString*.

Example of *SD* file containing atom types fingerprints string data:

```

... ..
... ..
$$$$
... ..
... ..
... ..
41 44 0 0 0 0 0 0 0 0 0999 V2000
-3.3652 1.4499 0.0000 C 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0
... ..
2 3 1 0 0 0 0
... ..
M END
> <CmpdID>
Cmpd1

> <AtomTypesFingerprints>
FingerprintsVector;AtomTypesCount:AtomicInvariantsAtomTypes:ArbitrarySi
ze;10;NumericalValues;IDsAndValuesString;C.X1.B01.H3 C.X2.B02.H2 C.X2.B
O3.H1 C.X3.B03.H1 C.X3.B04 F.X1.B01 N.X2.B02.H1 N.X3.B03 O.X1.B01.H1 O.
X1.B02;2 4 14 3 10 1 1 3 2

$$$$
... ..
... ..

```

Example of *FP* file containing atom types fingerprints string data:

```
#
# Package = MayaChemTools 7.4
# Release Date = Oct 21, 2010
#
# TimeStamp = Fri Mar 11 14:28:07 2011
#
# FingerprintsStringType = FingerprintsVector
#
# Description = AtomTypesCount:AtomicInvariantsAtomTypes:ArbitrarySize
# VectorStringFormat = IDsAndValuesString
# VectorValuesType = NumericalValues
#
Cmpd1 10;C.X1.BO1.H3 C.X2.BO2.H2 C.X2.BO3.H1 C.X3.BO3.H1 C.X3.BO4 F...
Cmpd2 9;C.X1.BO1.H3 C.X2.BO2.H2 C.X3.BO3.H1 C.X3.BO4 N.X1.BO1.H2 N....
... ..
... ..
```

Example of CSV *Text* file atom types containing fingerprints string data:

```
"CompoundID", "AtomTypesFingerprints"
"Cmpdl", "FingerprintsVector;AtomTypesCount:AtomicInvariantsAtomTypes:Ar
bitrarySize;10;NumericalValues;IDsAndValuesString;C.X1.BO1.H3 C.X2.BO2.
H2 C.X2.BO3.H1 C.X3.BO3.H1 C.X3.BO4 F.X1.BO1 N.X2.BO2.H1 N.X3.BO3 O.X1.
BO1.H1 O.X1.BO2;2 4 14 3 10 1 1 1 3 2"
O.X1.BO2;3 3 6 3 1 1 2 2 2"
... ..
... ..
```

Examples:

```
FingerprintsVector;AtomTypesCount;EStateAtomTypes;ArbitrarySize;11;Num
ericalValues;IDsAndValuesString;aaCH aasC aasN dO dssC sCH3 sF sOH ssC
H2 ssNH sssCH;14 8 1 2 2 2 1 3 4 1 3
```

```
FingerprintsVector;AtomTypesCount:SYBYLAtomTypes:ArbitrarySize;9;NumericalValues;IDsAndValuesString;C.2 C.3 C.ar F N.am N.ar 0.2 0.3 0.co2;29 22 1 1 1 1 2 2
```

```
FingerprintsVector::AtomTypesCount:SYBYLAtomTypes:FixedSize:44;OrderedNumericalValues;IDsAndValuesString:C.3 C.2 C.1 C.ar C.cat N.3 N.1 N.l .ar N.am N.pl3 N.4 O.3 O.2 O.co2 S.3 S.2 S.o S.o2 P.3 F Cl Br I ANY HAL L HET Li Na Mg Al Si K Ca Cr.th Cr.oh Mn Fe Co.oh Cu Zn Se Mo Sn;9 2 0 22 0 0 0 0 1 1 0 0 2 1 2 0 0 0 0 0 1 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0
```

`-w, --WorkingDir DirName`

Location of working directory. Default: current directory.

## EXAMPLES

To generate atomic invariants atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -r SampleATFP -o Sample.sdf
```

To generate functional class atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a FunctionalClassAtomTypes
-r SampleATFP -o Sample.sdf
```

To generate E-state atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a EStateAtomTypes
--AtomTypesSetToUse ArbitrarySize -r SampleATEFP -o Sample.sdf
```

To generate E-state atom types count fingerprints of fixed size in vector string with IDsAndValues format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a EStateAtomTypes
--AtomTypesSetToUse FixedSize -v IDsAndValuesString
```



```
-r SampleATFP -o Sample.sdf
```

To generate E-state atom types bits fingerprints of fixed size in bit-vector string format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesBits -a EStateAtomTypes
--AtomTypesSetToUse FixedSize -r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--AtomTypesSetToUse ArbitrarySize -r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of fixed size in vector string format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--AtomTypesSetToUse FixedSize -r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of fixed size in vector string with IDsAndValues format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--AtomTypesSetToUse FixedSize -v IDsAndValuesString
-r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types bits fingerprints of fixed size in bit-vector string format and create a SampleATFP.csv file containing sequential compound IDs along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesBits -a MMFF94AtomTypes
--AtomTypesSetToUse FixedSize -r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing compound ID from molecule name line along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--DataFieldsMode CompoundID --CompoundIDMode MolName
-r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing compound IDs using specified data field along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--DataFieldsMode CompoundID --CompoundIDMode DataField --CompoundID
Mol_ID -r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing compound ID using combination of molecule name line and an explicit compound prefix along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--DataFieldsMode CompoundID --CompoundIDMode MolnameOrLabelPrefix
--CompoundID Cmpd --CompoundIDLabel MolID -r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing specific data fields columns along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--DataFieldsMode Specify --DataFields Mol_ID -r SampleATFP
-o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of arbitrary size in vector string format and create a SampleATFP.csv file containing common data fields columns along with fingerprints vector strings data, type:

```
% AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
--DataFieldsMode Common -r SampleATFP -o Sample.sdf
```

To generate MMFF94 atom types count fingerprints of arbitrary size in vector string format and create SampleATFP.sdf, SampleATFP.fpf and SampleATFP.csv files containing all data fields columns in CSV file along with fingerprints vector strings data,

---

```
type:      % AtomTypesFingerprints.pl -m AtomTypesCount -a MMFF94AtomTypes
          --DataFieldsMode All --output all -r SampleATFP -o Sample.sdf
```

## AUTHOR

Manish Sud <msud@san.rr.com>

## SEE ALSO

InfoFingerprintsFiles.pl, SimilarityMatricesFingerprints.pl, AtomNeighborhoodsFingerprints.pl, ExtendedConnectivityFingerprints.pl, MACCSKeysFingerprints.pl, PathLengthFingerprints.pl, TopologicalAtomPairsFingerprints.pl, TopologicalAtomTorsionsFingerprints.pl, TopologicalPharmacophoreAtomPairsFingerprints.pl, TopologicalPharmacophoreAtomTripletsFingerprints.pl

## COPYRIGHT

Copyright (C) 2018 Manish Sud. All rights reserved.

This file is part of MayaChemTools.

MayaChemTools is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.